

S011.1303.4

Firmware Release Notes for the Nexsan E-Series P

Change notes from S011.1303.2 (S011.1303.3 was Hotfix release only)

Release Date: 5th February 2019

Notes

Nexsan warrants that the software portion of its E-Series brand Products, when delivered and properly installed at customer site, will perform materially in accordance with Nexsan's published Specification for a period of thirty (30) days after delivery, except for non-material aesthetic aspects. Nexsan will replace any defective media item within thirty (30) days after delivery. Nexsan does not warrant that the functions contained in the software will meet any requirements beyond the Product Specifications, or that the operation of the software will be uninterrupted or error free. Nexsan makes no representation as to the suitability of Software supplied as to fitness for a particular purpose.

Nexsan will make available free of charge to the original registered owner of the Product any software updates and maintenance releases which are issued during the warranty, or contracted support period. These updates are available from Nexsan Product Support and may only be available if the system has been registered through the on-line or GUI process. Nexsan warrants that it is authorized to grant the license to the Software herein to the Licensee. Any consulting or other services provided by Nexsan are on a best efforts basis. Nexsan does not warrant that any of the Items will meet the specific needs of the Licensee.

THE FOREGOING WARRANTIES ARE IN LIEU OF ALL OTHER WARRANTIES, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO, IMPLIED WARRANTIES OF FITNESS FOR A PARTICULAR PURPOSE AND WARRANTIES OF MERCHANTABILITY. NEXSAN SPECIFICALLY DENIES ANY IMPLIED OR EXPRESS REPRESENTATION THAT: (i) ANY OF THE ITEMS WILL FIT THE LICENSEE'S REQUIREMENTS; (ii) THE SOFTWARE WILL OPERATE UNINTERRUPTED OR ERROR-FREE; OR (iii) LICENSOR CAN HAVE ALL PROGRAM DEFECTS CORRECTED.

IMPORTANT: WARNING: Any replication partner systems will also need to be running software revision S011.1302 or higher (or in the case of E-Series V/VT the software revision R011.1207 or higher is required; for 3Gb E-Series use Q011.1207 or higher) to continue to support volume replications. **Replication now uses the standard iSCSI TCP port 3260;** the use of TCP port 44846 has been deprecated.

IMPORTANT: Rolling Restart must **NOT** be used if the system is being **upgraded** from S011.1300.3 (or earlier) or S011.1301.1 **and** has Self Encrypting Drives in use in Encrypted Arrays. A Reboot restart is required. Please contact Nexsan Support for further details.

IMPORTANT: Hot restart available from S011.1303.2

This software is released for all versions of Nexsan E-Series P.

New Features in Version S011.1303.4

Description
<ul style="list-style-type: none">• None

Enhancements in Version S011.1303.4

Description
<ul style="list-style-type: none">• None

Bugs fixed in Version S011.1303.4

Description	Reference
Replication <ul style="list-style-type: none">Prevent internal resource leak each time a replication session was openedHandle the case where closing an iSCSI session fails as it's already been closed (prevents "unused data" log)Prevent memory leaks when opening outbound iSCSI sessions	47690 ESS-424
Encryption <ul style="list-style-type: none">Ensure RAID operations (move, delete etc) are allowed to complete after encrypting an array	47813 Bug 1533

Contact Information

North American Headquarters, USA
Nexsan
910 E Hamilton Ave, Campbell,
CA 95008, United States

Technical Services:
North America: 866-2-NEXSAN
(1.866.263.9726)
Worldwide: 1.760.690.1111

European Headquarters, United Kingdom
Nexsan
Units 33-35 Parker Centre, Mansfield Road
Derby, DE21 4SZ,

UK Technical Services:
From Europe: +44 (0)1332 291600
Worldwide: 1.760.690.1111

E-mail: support@nexsan.com or sales@nexsan.com